

PC Connect installation and use

By installing the PC Connect software recorded on the CASSIOPEIA Software Applications CD-ROM, the CASSIOPEIA BE-300 can synchronize Calendar, Contacts, Tasks and Mail information through corresponding data standards that work with Microsoft Outlook 97/98/2000 on a personal computer. The following operations will be possible after finishing installation to the computer. These functions will not be available if Outlook is not installed on the computer.

Other functions are :

- Synchronizing of Web pages saved on the PC with companion pages on the BE-300.
- Synchronizing of optional PC folders with folders on the BE-300.
- Installation of additional software for the BE-300 recorded on the CD-ROM.
- Restoring a current backup of data to the BE-300.
- Restoring the entire BE-300 to its original condition.

It is necessary to complete the installation before connecting the CASSIOPEIA to the PC. It is strongly recommended that the software be installed as the first action taken after purchase.


Do not connect the CASSIOPEIA to the computer until software installation has been completed.

Installing PC Connect software onto CASSIOPEIA


Close all running applications on the PC before performing the following operations.

- (1) Place the CASSIOPEIA Software Applications CD-ROM into the CD drive of the PC.
- (2) The following window should automatically appear on the computer screen. If the window does not appear after waiting for a short period of time, use File Explorer to view the contents of the CD-ROM and double-click the "menu.exe" file in the file list.


- (3) Click [Software List] in the opened window.



- (4) In the software list, click on "# PC Connect" to select it, and then click [Install]. Continue by following the instructions that appear on the screen.




- (5) When installation has finished, the following window will appear. Click [Finish].
The computer will automatically restart. While restarting, remove the CD-ROM from the computer.




Setting up Data Synchronize for the computer with PC Connect

- (1) After the computer has restarted, firmly insert the USB cradle's connector into the USB port of the PC.
- (2) Place the CASSIOPEIA on the USB cradle and turn it on. If the CASSIOPEIA is already on when placed on the cradle, leave it on.
- (3) The following PC Connect window will appear on the computer screen.




Wait for the synchronization symbol, shown in the red circle below, to appear on the screen of the CASSIOPEIA.




If the synchronization symbol does not appear after a short period of time, reconnect the USB cable to the USB port on the PC and reconnect the CASSIOPEIA to the cradle.


- (4) On the computer screen window, click "Settings" and then click "Data Synchronization Settings". the following window will open.



- (5) In the following window, click the application you want to synchronize between the PC and the CASSIOPEIA. It will become shaded. Click [Choose], and the "Choose Translator" window will appear.




- (6) Click "MS Outlook" to select it from the "Available Translators" list.



- (7) Because the basic settings for MS Outlook will be sufficient for now, click [OK]. To learn more about settings, click [Help] and refer to the displayed information.

- (8) The "Intellisync for CASSIOPEIA Configuration" window will reappear, and a check will appear in the "Calendar" checkbox.



Data synchronization is set between CASSIOPEIA Calendar <---> MS Outlook Calendar. Tasks, Mail and Contacts to Outlook synchronization settings can be set with the same method. Select the applications you need and complete the settings.


To make the synchronization setting for mail, it will be necessary to set a mail account in the "Mail" software in addition to having the setting for software connection and mail connectivity already in CASSIOPEIA "Connections".

When several mail accounts have been set in the CASSIOPEIA, a mail account setting window will appear when making synchronization settings and one account must be selected for synchronization.


- (9) When all needed synchronization settings have been made, click [OK]. The "Intellisync for CASSIOPEIA Configuration" window will close. This completes "PC Connect" installation and basic settings.

Executing Data Synchronize with the computer

- (1) Place the CASSIOPEIA on the USB cradle and turn it on. If the CASSIOPEIA is already on when placed on the cradle, leave it on.
- (2) The following PC Connect window will appear on the computer screen.




Wait for the synchronization symbol, shown in the red circle below, to appear on the screen of the CASSIOPEIA.




If the synchronization symbol does not appear after a short period of time, reconnect the USB cable to the USB port on the PC and reconnect the CASSIOPEIA to the cradle.


- (3) Click the [Synchronize] button in the PC Connect window on the computer screen.
(In the red circle above.)



- (4) Synchronization with the computer will start, and a progress bar will appear, as shown below. The synchronization process will take some time, depending on how much data is to be transferred.



- (5) When synchronization is finished, the PC Connect window will change as shown below and data synchronization with Outlook will be completed.



- (6) In the "Main" menu on the CASSIOPEIA, double-tap one of the applications that had data synchronized, such as Calendar or Mail. The data on the CASSIOPEIA should be arranged in the same way as on the computer. (Content items may differ according to content settings.)

To learn about more detailed use of "PC Connect" software, start "PC Connect" and click "Help" on the window. Refer to the help file.