

Transferring other types of data to CASSIOPEIA


Optional data files can be transferred to CASSIOPEIA with PC CONNECT, when transferring files other than music, photo or movie files. "Quick View Plus®," included on the CASSIOPEIA Software Applications CD-ROM, enables viewing of data files such as those created by Microsoft Office.

First follow the instructions at "PC Connect installation and use" to install specialized "PC Connect" software recorded on the CASSIOPEIA Software Applications CD-ROM. Also link the CASSIOPEIA and the computer by connecting the included USB cradle to the computer.


(This installation and connection only needs to be done one time.)

Transferring various data files to CASSIOPEIA

- (1) Place the CASSIOPEIA on the USB cradle and turn it on. If the CASSIOPEIA is already on when placed on the cradle, leave it on.
- (2) The following PC Connect window will appear on the computer screen.




Wait for the synchronization symbol, shown in the red circle below, to appear on the screen of the CASSIOPEIA.




If the synchronization symbol does not appear after a short period of time, reconnect the USB cable to the USB port on the PC and reconnect the CASSIOPEIA to the cradle.


- (3) On the computer screen window, click "Settings" and then "Folder Synchronization Settings...", and the Folder-Folder Settings window will open.



- (4) In the following window, click the [Add] button. The “Input Folder Set Name” window will appear.



- (5) Type a name for the new Folder Synchronization Setting in the field shown by the red circle in the window below. The name “OfficeData” is used in this example.



- (6) After entering the name, click [OK]. The “Folder Synchronization Settings (Detail)” window will appear.

Folder Settings

Files in the following folders will be synchronized.

Folder location on CASSIOPEIA:
Nand Disk\My Documents\OfficeData Browse...

Folder location on this PC:
C:\CASSIOPEIA\OfficeData Browse...

Operation

☐ Import files ☐ Export files ☒ Synchronize files
☐ Synchronize files for Web Pages

Option

☐ Copy/Synchronize files in sub folders

OK Cancel

- (7) In the window, enter information as explained below. After completing the settings, click [OK].

In this example, the following names are entered. (It does not matter which name is entered first.)

PC folder --> “C:/CASSIOPEIA/OfficeData”

CASSIOPEIA folder --> “Nand Disk/My Documents/OfficeData”

About the data fields:

- PC Folder

A name entered here will result in automatic creation of the folder on the PC. If an existing folder is mistakenly selected, the unwanted contents of that folder will be transferred to CASSIOPEIA during synchronization.

- CASSIOPEIA Folder

As with PC Folder creation, a new folder name entered here will result in the folder being automatically created on CASSIOPEIA. If a new folder is wanted on the CF card, change the name in this field from “Nand Disk/My Documents” to “Storage Card/My Documents.”

- Control [P]: “Synchronize”

This setting will result in complete matching of all folder contents between the CASSIOPEIA and the PC when performing a synchronization. However, a file deleted for the folder on the PC side will not delete the matching file on the BE-300. To delete BE-300 files, use the corresponding application or “File Manager.”

To install the “File Manager” software on the BE-300, see the installation steps described in the other following document:

Listening to music on CASSIOPEIA


At Step 6 in this process, select “File Manager” from the software list, and then continue with the additional installation steps.

Select the “Import” option to copy files from the PC to CASSIOPEIA, or select “Export” to copy files from CASSIOPEIA to the PC.


- Option: None

When the “SubFolder Sync/Transfer” checkbox is checked, any subfolders present in the designated transfer folder will also be synchronized or copied. There is the potential to accidentally transfer many files to CASSIOPEIA if this is on, so keep this off in normal circumstances.


- (8) The “Folder Synchronization Settings” window will reappear. Confirm that a checkmark has been placed in the box for the folder to be synchronized, and then click [OK]. This completes setting of the optional folder for data transfer.




- (9) Click the [Synch] button (shown in the red circle below), and the folders that did not already exist when they were set in Step 7 will be automatically created.



- (10) Put files you want to copy to CASSIOPEIA into the PC folder that was created by Step 9. (Folder example: C:/CASSIOPEIA/OfficeData) Then click the [Synch] button again.



- (11) Synchronization will start, and the windows shown below will appear.



- (12) When synchronization is complete, the PC Connect will appear as shown below, and the data files in the designated folder will have been transferred.
- (13) Start the needed application on CASSIOPEIA to read or use the transferred data files. In the application, select the data file for use.

To learn about more detailed use of “PC Connect” software, start “PC Connect” and click “Help” on the window. Refer to the help file.